

ADISRA® SmartView

How to Install and Run the Viewer

Document Information

Software Version:	4.0.3.5
Creation Date:	August, 2022
Last Edit Date:	18, August, 2022
Version:	1.0
	97



1. Purpose of this article

This article aims to show you how to install and run Viewer.

2. How to Install Viewer

ADISRA SmartView requires .NET 5 to run. Please follow the direction below to install the .NET 5 and ADISRA SmartView.

1. Install the ASPNET Core Runtime (x64 or x86) located in the installation folder.

📙 🔄 🔜 🖛 ADISRA SmartView	_	×
File Home Share View		~ ?
← → · ↑ 🔄 › ADISRA Smar › · ♂ O Search ADISRA SmartView		
1. ADISRA SmartView Pre-requisites_OPCCoreComponents_x64		
1. ADISRA SmartView Pre-requisites_OPCCoreComponents_x86		
2. ADISRA SmartView Pre-requisites_AspnetcoreRuntime_x64		
2. ADISRA SmartView Pre-requisites_AspnetcoreRuntime_x86		
3. ADISRA SmartView Pre-requisites_WindowsdesktopRuntime_x64		
3. ADISRA SmartView Pre-requisites_WindowsdesktopRuntime_x86		
ADISRA SmartView		
(China		

2. Install the Windows Desktop RunTime (x64 or x86) located in the installation folder.

📙 🔄 📙 🛨 ADISRA SmartView	_	×
File Home Share View		~ ?
\leftarrow \rightarrow \checkmark \bigstar ADISRA Smar \checkmark \checkmark \eth \checkmark Search ADISRA SmartView		
1. ADISRA SmartView Pre-requisites_OPCCoreComponents_x64		
1. ADISRA SmartView Pre-requisites_OPCCoreComponents_x86		
2. ADISRA SmartView Pre-requisites_AspnetcoreRuntime_x64		
2. ADISRA SmartView Pre-requisites AspnetcoreRuntime x86		
3. ADISRA SmartView Pre-requisites_WindowsdesktopRuntime_x64		
3. ADISRA SmartView Pre-requisites_WindowsdesktopRuntime_x86		
a ADISRA SmartView		



3. After installing the above frameworks, click on the executable "ADISRA SmartView.exe" to install the ADISRA SmartView. Run the installer as administrator.



3. How to run Viewer

1. After installing Viewer, open the viewer as shown in the image below.

1000	All Apps Documents Web M	iore 🔻		×
1000	Best match			
	Viewer 2		A	
	Apps		Viewer	
20	🙆 3D Viewer		Арр	
100	Event Viewer			
N	Settings		다 Open	
100	윤 Turn on Diagnostic Data Viewer		🗟 Run as administrator	
8	🖙 Choose a default photo viewer		Den file location	
100	Search the web		-⇔ Pin to Start	
	P TeamViewer - Computer Software		-⇔ Pin to taskbar	
			🗓 Uninstall	
	𝒫 viewer autodesk			
	,∕⊂viewership			
1	,∕⊂ viewer boss			
	,			
	♀ viewerlabs			
-				

A configuration window will open containing the following settings:
IP: Enter the IP of the runtime machine

Port: The port used for communication between the viewer and the runtime. Keep port 9002. **Force Project Download:** Check this option to save the application in the viewer machine. Once this is done, navigation between screens will be faster.

Save Configuration: If checked, all settings in the viewer settings window will be saved. Custom Resolution: Sets the resolution of the viewer.

Test Connection Button: Tests the connection between the viewer machine and the runtime machine.

Connect Button: Opens the viewer Initial Screen. The first opening of the viewer may take a while, as the screens will be downloaded.

🔭 Vi	ewer	—		×
IP:	192.168.0.110			
Port:	9002			
✔ Fo	rce project downl ve configuration	oad		
Cu	ustom Resolution:	● 640 ● w 1	0 x 480 280 н	720
	Test Connection	Co	nnect	

